

# CMIRIS2 SDK User Manual

Version 2.1.1 for ARM Linux (Linaro Ubuntu 12.04)  
for EMA-30 and ECU-30 Products

Sep 2014

**CMITech Company, Ltd.**  
#904, #905, K-Center, 25, Simin-daero 248beon-gil,  
Dongan-gu, Anyang-si, Gyeonggi-do, 431-815 Rep.of  
KOREA  
Tel: +82.70.8633.8277  
Fax: +82.31.624.4490  
Contact: [sales@cmi-tech.com](mailto:sales@cmi-tech.com)

**CMITech America, Inc.**  
2033 Gateway Place, Suite 500  
San Jose, CA 95110 USA  
Tel: (1) 408 573-6930

## Table of Contents

<b>1. History of Changes from Prior Versions of SDK's .....</b>	<b>3</b>
<b>2. Introduction .....</b>	<b>5</b>
<b>3. Mainboard and OS Description .....</b>	<b>6</b>
<b>4. CMIRIS SDK Implementation Guide .....</b>	<b>7</b>
4.1.....Create cmirisLib .....	7
4.2.....Get the initially attached devices .....	8
4.3.....Open the device .....	8
4.4.....Image preview, RGB indicator and image captured events .....	9
4.5.....Start capture .....	10
4.6.....“Either Eye” capture mode .....	10
4.7.....Auto capture .....	11
4.8.....Stop Capture .....	12
4.9.....Capture parameters .....	12
4.10.....Face color image conversion with libcmicolorLib_arm_0.9.0.so .....	12
<b>5. Reference Manual of Values, Definitions and API Functions of libcmirisLib2_arm_2.1.1.so .....</b>	<b>12</b>
5.1.....Defined Return Values .....	12
5.2.....Type Definitions .....	13
5.3.....API Functions .....	16
<b>6. MIRLIN Functions in cmirisLib2 .....</b>	<b>30</b>
<b>7. Testing the external I/O interface of EMA-30 or ECU-30.....</b>	<b>32</b>

## 1. History of Changes from Prior Versions of SDK's

- ◆ Version 2.0.3 was the initial public release, although units shipped under CMITech's EMA and ECU-30 beta program had earlier version of the operating libraries. All EMA-30 and ECU-30 units shipped before July 16, 2014 are supplied with the older version than v2.1.0.

### Changes in V2.0.3

- ◆ There was a bug in ARM Linux cmirisLib2 library that made EMA / EMB units freeze during capture process. This bug has been temporarily fixed and it will require a firmware upgrade for fundamental improvement. All new production units shipped since May 1, 2014 have the current version of firmware for the EMA and EMB, which is 1.2.16.
- ◆ In the released SDK, all folders have been moved under /usr/local/. Please copy all the folders into /usr/local/ and set file's attribute appropriately. cmirisLib\_arm\_1.1.3.so without MIRLIN algorithm is also released which is used by EMXDemo.
- ◆ Known bug: In EMXDemo, USB removal is handled correctly but it is not in CMIMIRDemo. This bug is under investigation.
- ◆ Note: "dmesg" will show the kernel message "usb 1-2.1.2: usbfs: usb\_submit\_urb returned -121" after the capture process. This message is not error but USB debug message and will be off in the release version of Linux.
- ◆ Note: "libcmirisLib2\_arm\_2.0.3.so" was linked with /lib/libusb-1.0.so.2 (libusb-1.0.so.2.0.0) which must reside in the folder /lib. There is another libusb-1.0.so in the folder /lib/arm-linux-gnueabi/libusb-1.0.so.0 (libusb-1.0.so.0.1.0) which is the older version.

### Changes in V2.1.0

- ◆ Most bugs were fixed including lockup problem during operation. The new cmirisLib2 library will survive with the frequent USB removal and arrival actions. But in artificial testing, this may cause the USB driver to crash in ECU-30 which cannot be recovered without system reboot. In order to recover the system automatically, "emaUsbMonitor" for EMA-30 and "ecuUsbMonitor" for ECU-30 will be also provided, which will monitor USB status. If something goes wrong in USB driver, it will reboot the EMA-30 or ECU-30. The "emaUsbMonitor" should be found in the folder /usr/local/bin and  
"/usr/local/bin/emaUsbMonitor >> usbMonitorLog start" should be added at the last line of /etc/rc.local to make it run as a daemon. It should be noted that "emaUsbMonitor" is also necessary for EMA-30, even though there is no chance for USB cable disconnections.
- ◆ Face tracking performance on EMA-30 and EMB-30 has been improved.
- ◆ Capture process has been optimized for faster performance.
- ◆ libcmirisLib\_arm\_1.x.xx.so without MIRLIN Algorithm will not be released any more, since libcmirisLib2\_arm\_2.x.xx.so is libcmirisLib\_arm\_1.x.xx.so plus the MIRLIN Algorithm.
- ◆ Move up/down and press/release events are added in Device Manager Event.

- ♦ Auto adjustment of target intensity was added to avoid sclera saturation in small percentage of subjects, thereby improving FTC rate.
- ♦ The current indicator color is now available in the field of leftPosition or rightPosition in “CMI\_IMAGE\_INFO” structure for additional feedback to user.
- ♦ Rare case of software failure when motor is opened was fixed.
- ♦ Rare case of software failure (lockup) for “cmi\_closeDevice()” problem was fixed.
- ♦ Other minor bugs were fixed.
- ♦ Positioning color indication (blue, green, red) was significantly improved to be more responsive and eliminate occasional error in indicator when subject was too close.
- ♦ Iris image margins were set as specified in ISO/IEC 19794-6:2011(E), so that the capture area (X and Y dimensions, not Z) was increased.
- ♦ Two voice cues were implemented: "Please come closer" and "Please move back". To support voice cues, the new event “CMI\_EVENT\_INDICATOR” was added, which notifies the indicator color change (blue or red) and the moment when the voice cue should be played. Voice cue sound files are .wav files that can be customized by customer for language or other preferences.
- ♦ Either Eye mode was added. In this mode, device tries to capture both eyes first and if the number of frames elapsed after one eye is captured exceeds “maxFrameDiffinEitherEyeMode”, then device just returns image from only one eye. “maxFrameDiffinEitherEyeMode” can have the values from 3 to 9, referring to the number of frames. Rare case of failure in motor open was fixed.
- ♦ The new option whether to return to the initial motor position after successful capture was added. It can be enabled or disabled using cmi\_setMotorReturnToInitEnabled() before cmi\_startCapture() is called.
- ♦ CMIMIRDemo will now allow either eye enrollment and recognition.

#### Changes in V2.1.1

##### EMX Family:

- ♦ The depth of field is now adjustable with cmi\_setDepthOfField().
- ♦ The center of depth of field is 330mm from the front surface of EMX.
- ♦ The minimum and default of each depth of field is 15mm, so total depth of field is 30mm. This is the depth of field for enrollment.
- ♦ The maximum is 35mm for inside and 25mm for outside, total maximum depth of field is 60mm, which is for recognition for physical access control application.

## 2. Introduction

This CMIRIS SDK for Linux user manual describes the SDK for CMITECH's EMA-30 and ECU-30 products, which are intended for physical access control applications. These products share the same embedded mainboard that runs the Linaro Ubuntu 12.04 operating system and utilize CMITech's Linux operating libraries.

The core of CMIRIS SDK is the Iris image capture library, "libcmirisLib2\_arm\_2.1.1.so". This main operating library was compiled from the Windows version of the same library, and is intended to have the exact same core functionality in image capture and control functions as the Windows version.

The EMA-30 and ECU-30 also have the option for embedded iris image encoding and matching functions based on the Smart Sensors, Ltd. MIRLIN algorithm. This functionality is embedded into the libcmirisLib2\_arm\_2.1.1.so library, but it is enabled by a switch in the firmware of the EMA-30 or EMB-30 (which would be attached to the ECU-30) cameras. This switch is set at product setup time in the CMITech production operation.

There are only 2 other operating libraries supplied with the EMA-30 and ECU-30 and one of them is "libemaLib\_arm\_1.0.1.so". This library enables you to control all the I/O functions that EMA-30 or ECU-30 has, such as Wiegand I/O, GPIO, Relay and RS485. The test application "emaTest" and its source code, provided in the folder /usr/local/bin and /usr/local/src/CMITECH respectively, show how to use this library. The detailed description on "emaTest" application can be found in "/usr/local/doc/EMA\_EMB\_ECU\_Quick\_User\_Guide\_V2.1.1.pdf".

The other library is "libcmicolorLib\_arm\_0.9.0.so" and it manages the color face imaging function, which converts Bayer raw color images to RGB images. However, the color face image is not supported in Linux OS at this moment and this library is included for compatibility with Windows version.

Another demo application loaded onto the EMA-30 and ECU-30 is "CMIMIRDemo" which shows each functions of libcmirisLib2\_arm\_2.1.1.so library. The simple description on this demo application can be found in the quick user guide document addressed above and the source code of this demo can be found in the folder /usr/local/src/CMITECH.

Also please note that the BMT-20 product is principally compatible with the Linux OS, but this release (v2.1.1) does not cover the BMT-20 product. Please contact CMITech for more information.

CMIRIS2 SDK distribution contains the following directories and files:

## **/usr/local**

**/doc** - contains all the documents for the CMIRIS2 Linux SDK.

**/bin** - contains executable files for demo application as “CMIMIRDemo” and “emaTest”. In addition, “emaUsbMonitor” for EMA-30 and “ecuUsbMonitor” for ECU-30 are also provided, which will monitor USB status. If something goes wrong in USB driver, it will make the EMA-30 or ECU-30 to reboot. In order to make it run as a daemon “/usr/local/bin/emaUsbMonitor >> usbMonitorLog start” should be added at the last line of /etc/rc.local. It should be noted that “emaUsbMonitor” is also necessary for EMA-30, even though there is no chance for USB cable disconnections.

**/include** – contains header files including cmiglobal.h, cmirislib2.h, emaglobal.h, emalib.h and cmicolorlib.h. The suffix “2” denotes the functionality for the embedded MIRLIN encoding and matching.

**/lib** – contains the 3 operating libraries, libcmirisLib2\_arm\_2.1.1.so, libcmicolorLib\_arm\_0.9.0.so, and libemaLib\_arm\_1.0.1.so.

**/share** - the folder “CMITECH” under /share contains the haarcascades folder, the .wav files for vocalizations. The CMIMIRDemo application data base “Enroll.db” will be created if it does not exist. To reset the database, the existing “Enroll.db” can be just deleted.

**/src** – the “CMITECH” folder contains the source code for the Linux demo application to serve as sample code.

### **3. Mainboard and OS Description**

The CMITech operating libraries as described in this SDK have been implemented on a custom designed mainboard featuring the Samsung Exynos 4412 quad-core CPU / SOC with 2 GB of RAM and 16 GB of flash memory, and the Linaro Ubuntu 12.04 OS. This mainboard also includes all physical connectors necessary for a fully functional physical access control system, including dual Wiegand, RS 232 and 485 serial ports, GPIO and high current relay connectors.

For implementation of this SDK on a different hardware platform, please contact CMITech directly.

It is the company’s policy at this time to support only the Linaro Ubuntu 12.04 OS distribution.

## 4. CMIRIS SDK Implementation Guide

The CMIMIRDemo application shows most of the features that the CMIRIS SDK has. Please refer to the source code in /usr/local/src/CMITECH folder for details.

In general, because the operating library for the Linaro Ubuntu SDK is virtually identical in functionality to the equivalent in the CMITech Windows SDK, the Implementation Process, Defined Returned Values, and Type Definitions descriptions are the same.

However, there are additional functions and calls for the added functionality of the embedded MIRLIN encoding and matching functions. Please refer to section 6. MIRLIN Functions in cmirisLib2 in this document.

### Recommended SDK Implementation Process Steps

#### 4.1. Create cmirisLib

```
#include "cmirislib2.h"

if (cmi_createCMIRis(CMI_DMx_EMx_MODEL, &m_cmiHandle) == CMI_SUCCESS) {
    m_dmEventThread = new DMEventThread(NULL, m_cmiHandle);
    if (m_dmEventThread) {
        connect(m_dmEventThread, SIGNAL(deviceRemoved(CMI_DEVICE_INFO *)),
            this, SLOT(doDeviceRemoved(CMI_DEVICE_INFO *)));
        m_dmEventThread->start();
        ...
    }

    m_eventThread = new EventThread(NULL, m_cmiHandle);
    if (m_eventThread) {
        connect(m_eventThread, SIGNAL(preview(CMI_IMAGE_INFO *)),
            this, SLOT(doPreview(CMI_IMAGE_INFO *)));
        ...
    }
}
```

First of all, `cmi_createCMIRis(CMI_DMx_EMx_MODEL, &m_cmiHandle)` must be called to create the cmirisLib instance and create the handle for it. For DMX-30 and EMX-30 devices, the first argument should be `CMI_DMx_EMx_MODEL`, and for the BMT-20 it should be `CMI_BMT_MODEL`. Once cmirisLib instance is created, the device manager will run inside to detect device removal, arrival, power suspend and resume. The devices which have already been connected with the call, `cmi_createCMIRis()`, will be available as the device arrival events happen. These events can be read by `cmi_readDMEvent(CMI_HANDLE handle, CMI_DM_EVENT *event, DWORD timeout)` in the separate thread loop just after the function call `cmi_createCMIRis()`. Please refer to `dmeventthread.cpp` for reading device

manager event, `CMI_DM_EVENT`, as defined in `cmiglobal.h`.

## 4.2. Get the initially attached devices

After the successful creation of `cmirisLib`, it is necessary to read the device manager event to find the currently attached devices. In the `EMXDemo` application, this initial set up is handled in `doDeviceArrived(CMI_DEVICE_INFO *deviceInfo)`, which is the “slot” and will be called whenever `cmi_readDMEvent()` receives the device arrival event. “Signal” and “Slot” are used for communication between objects in Qt and the detailed information can be found in the following link; <http://doc.qt.nokia.com/4.7-snapshot/signalsandslots.html>.

```
m_deviceInfoList << deviceInfo;
ui->comboBox_SerialNumbers->clear();
int index = 0;
for (i = 0; i < m_deviceInfoList.size(); i++) {
    ui->comboBox_SerialNumbers->addItem(QString(m_deviceInfoList.at(i)-
>serialNumber));
    if (QString(m_deviceInfoList.at(i)->serialNumber) == comboSN) {
        index = i;
    }
}
ui->comboBox_SerialNumbers->setCurrentIndex(index);
```

In the above sample code, each arrived `deviceinfo` is stored in `m_deviceInfoList` and the serial number of device will be shown in the combo box menu for user’s selection. The device arrival and removal event during operation will be handled in `doDeviceArrived()` and `doDeviceRemoved()`.

## 4.3. Open the device

```
int ret = cmi_openDevice(m_cmiHandle, dvInfo);
```

`cmi_openDevice()` requires the `CMI_DEVICE_INFO` pointer in the second argument found in the device arrival event. If multiple devices are detected, one of devices should be selected by application. If one device is opened already, it will return

`CMI_ERROR_DEVICE_OPENED` error when another device is attempted to be open.

`CMI_DEVICE_INFO` has a following structure.

```
typedef struct _CMI_DEVICE_INFO {
    int cbSize; // size of this struct
    char modelName[CMI_MODEL_NAME_MAX_SIZE+1]; // BMT-20
    char serialNumber[CMI_SERIAL_NUMBER_MAX_SIZE+1]; //AA1105AA000128
    char hardwareRev[CMI_HARDWARE_REV_MAX_SIZE+1]; // 1.0.1
    char firmwareRev[CMI_FIRMWARE_REV_MAX_SIZE+1]; // 1.0.86
} CMI_DEVICE_INFO;
```



#### 4.4. Image preview, RGB indicator and image captured events

```
m_eventThread->start();
```

After the successful opening of the device and before starting capture, the thread loop reading image preview events and image captured events should be started. The function `cmi_readEvent(m_cmiHandle, &event, 100)` inside the thread loop in `eventthread.cpp` will read these events and send them to main GUI through “emit”. Each preview event will contain the image and image information, and the image uses the memory already allocated by application. Please see the section 3.5 below how to allocate the memory buffer for the images in these events.

After the application finishes, in order to use the image that comes with the preview event (after it displays the preview image on the monitor), the memory should be released by the function `cmi_releasePreviewBuffer(m_cmiHandle, image)`. Otherwise, the successive preview events cannot use this particular buffer area for the next preview events. If the buffer is not available on time, the preview event will contain the image information only, but not image itself. It should be noted that each preview event contains only one image. Please refer to the function `displayLiveImage (CMI_IMAGE_INFO *imageInfo)` in `mainwindow.cpp`.

For the events of `CMI_EVENT_IRIS_IMAGE_UNSELECTED` and `CMI_EVENT_IRIS_IMAGES_SELECTED`, the image buffer doesn’t need to be released, since these buffer areas are dedicated to the captured images and not reused.

With Linux SDK Version 2.1.1, there is a new event type `CMI_EVENT_INDICATOR`, which is introduced to implement vocal positioning cues of “move closer” and “move back” to the subject. This event notifies when the RGB indicator color was changed and when to play vocal cues. When this event occurs, `leftPosition` and `rightPosition` in `imageInfo` structure contains the RGB color information (`CMI_INDICATOR_COLOR_OFF`, `CMI_INDICATOR_COLOR_RED`, ...) and which vocal cue (`CMI_VOICE_COME_CLOSER`, `CMI_VOICE_MOVE_BACK`) should be played. No image will be returned in this event, so `leftImage` and `rightImage` in `imageInfo` structure should be NULL and `cmi_releasePreviewBuffer(CMI_HANDLE handle, unsigned char *buffer)` should not be called. The event values are defined in `cmiglobal.h`.

In order to utilize this `CMI_EVENT_INDICATOR`, you need to enable this event using the function `cmi_setIndicatorEventEnabled(CMI_HANDLE handle, int enabled)`, since the default is disabled for backward compatibility. The time interval of vocal cues can be adjusted with the function `cmi_setVoiceCueTimeInterval(CMI_HANDLE handle, int firstTimeInterval_frames, int nextTimeInterval_frames)`, where the time interval is in the unit of frame number, i.e. 33ms. The default value of `firstTimeInterval_frames` is 75 and 90 for `nextTimeInterval_frames`.

`firstTimeInterval_frames` is the first vocal cue time interval and `nextTimeInterval_frames` will determine the time interval thereafter.

#### 4.5. Start capture

```
if (!m_applBuffer) {
    cmi_getBufferSize(m_cmiHandle, 10, MAX_UNSELECTED_RECT,
        &m_applBufferSize);
    m_applBuffer = new unsigned char [m_applBufferSize];
}
int ret = cmi_startCapture(m_cmiHandle, m_applBufferSize, m_applBuffer);
```

Before starting the capture process, the application should allocate buffer space to store the preview and captured images. To find the buffer size for these images, the function `cmi_getBufferSize()` should be called before the function `cmi_startCapture()`. The function `cmi_getBufferSize()` calculates the buffer size using the number of preview images and the number of unselected images, and will set the necessary internal parameters. After the function `cmi_openDevice()` is called, the function `cmi_getBufferSize()` must be called at least once. As for BMT-20, `cmi_setBMTMode()` should be called before `cmi_getBufferSize()`, since CMI\_BMT\_USER\_MODE providing the full resolution preview images requires more buffer size.

The “unselected” images are the captured images within the operating range that were not selected as two (left and right irises) final captured images by the CMIRIS SDK capture algorithm. These unselected images are provided to be used by the application in the case that the CMIRIS SDK capture algorithm has not picked the best images. These unselected images are only available in DMX-10 and EMX-10, but not in BMT-20. In the EMXDemo application, these unselected images will be also saved when the save button is clicked. For faster capture speed, please set the argument “`maxNumUnselectedImages`” to zero.

#### 4.6. “Either Eye” capture mode

In Linux SDK Version 2.1.1, “Either Eye” capture mode is introduced to allow subjects with only one eye to be imaged. This is in addition to “Both”, “Left”, and “Right” eye capture modes. In the “Either Eye” mode, the device tries to capture both eyes for a certain period of time. But if it is able to capture only one eye during this period, it just returns the single captured eye with a face image.

The waiting time interval to capture the other eye once the first eye is captured is determined with the value of `maxFrameDiffInEitherEyeMode` in the function `cmi_setMaxFrameDiff InEitherEyeMode(CMI_HANDLE handle, int maxFrameDiffInEitherEyeMode)`. The minimum value of this parameter is 3 which mean that the captured left and right image frame difference allowed for both eye capture is 3, and if not, the only one eye captured is returned. The maximum value is set to 9, which is

the slowest option.

#### 4.7. Auto capture

After starting the capture process, a preview event will not be issued until a subject is detected by the device. The preview event is the type of `CMI_EVENT` with the event value `CMI_EVENT_PREVIEW_FRAME_INFO`.

```
typedef struct _CMI_EVENT {
    int cbSize;
    int event;
    CMI_IMAGE_INFO imageInfo;
} CMI_EVENT;
```

`CMI_IMAGE_INFO` contains the left iris, right iris, and face image with respective image information. Please refer to `cmiglobal.h` for the definition of `CMI_IMAGE_INFO`. As for the iris images, only one of the left and right iris image is alternatively available for each preview event. If there is no preview image buffer available which the application allocated, the image pointer will be `NULL` and the image width and height are 0's. Please make sure the used image buffer is released by the function call `cmi_releasePreviewBuffer()`. If the image or its information is not available, the value of each element will be one of `NULL`, 0, -1, `CMI_UNKNOWN`, or `CMI_EYE_UNKNOWN`.

If the CMIRIS SDK capture algorithm finds both iris images which satisfy the given requirements, such as maximum XY and Z movement restrictions, it will send the `CMI_EVENT_CAPTURE_DONE` event, so that the application can provide an audible or visible feedback to the subject. In this event, no image and image information will be provided in `imageInfo`. XY plane is defined as the plane parallel to the front surface of the device and Z direction is perpendicular to the front surface.

Right after the `CMI_EVENT_CAPTURE_DONE` event is sent to the application, the `CMI_EVENT_IRIS_IMAGE_UNSELECTED` and `CMI_EVENT_IRIS_IMAGES_SELECTED` will be followed successively. If `maxNumUnselectedImages` in `cmi_getBufferSize()` is set to 0, no `CMI_EVENT_IRIS_IMAGE_UNSELECTED` event will occur.

The `CMI_EVENT_IRIS_IMAGES_SELECTED` event contains the best left and right iris images selected by the CMIRIS SDK capture algorithm with image information. In addition to the iris images, the face image (360 x 480) captured just after 200 ~ 250 ms later will be stored in the "faceImage" pointer of `CMI_IMAGE_INFO`. The distance, XY-movement, Z-movement, inter-pupillary distance(IPD), iris center and radius in pixels will be provided. The unit of all lengths in `CMI_IMAGE_INFO` is  $\mu$ (micron) to avoid the floating value. The `rollAngle` and `rollAngleUncertainty` have not been implemented in this version of SDK.

## 4.8. Stop Capture

```
ret = cmi_stopCapture(m_cmiHandle);
```

This function will wait until all the images from the device are received and then clean the entire remaining preview and image captured events before it returns.

## 4.9. Capture parameters

Please refer to 4.3. API Functions for optional setting parameters.

## 4.10. Face color image conversion with libcmicolorLib\_arm\_0.9.0.so

At this time, color face is only supported in Windows OS, not in Linux OS. That is, it is not supported in either the EMA-30 or the EMB-30/ECU-30 combination. In the future, the face color image will be supported by the libcmicolorLib\_arm\_0.9.0.so library in Linux OS.

# 5. Reference Manual of Values, Definitions and API Functions of libcmirisLib2\_arm\_2.1.1.so

Please refer to “cmiglobal.h” and “cmirislib2.h” for the detailed information.

## 5.1. Defined Return Values

#define CMI_SUCCESS	0
#define CMI_ERROR_WAIT_TIMEOUT	-1
#define CMI_ERROR_READ_EVENT_CANCELLED	-2
#define CMI_ERROR_INVALID_HANDLE	-3
#define CMI_ERROR_INVALID_MODEL	-4
#define CMI_ERROR_FAIL_TO_SEND_COMMAND	-5
#define CMI_ERROR_INVALID_BUFFER	-6
#define CMI_ERROR_CALL_GET_BUFFER_SIZE_FIRST	-7
#define CMI_ERROR_BUFFER_SIZE_TOO_SMALL	-8
#define CMI_ERROR_CANNOT_FIND_DEVICE	-9
#define CMI_ERROR_DEVICE_OPENED	-10
#define CMI_ERROR_DEVICE_CLOSED	-11
#define CMI_ERROR_DEVICE_STARTED	-12

```

#define CMI_ERROR_DEVICE_STOPPED -13

#define CMI_ERROR_DEVICE_UPSIDE_DOWN -14

#define CMI_ERROR_IN_ARGUMENTS -15

#define CMI_ERROR_FAIL_TO_OPEN_IMAGER_DEVICE -16

#define CMI_ERROR_EEPROM_READ_TIMEOUT -17

#define CMI_ERROR_FAIL_TO_OPEN_MOTOR_DEVICE -18

#define CMI_ERROR_EEPROM_VERSION_INVALID -19

#define CMI_ERROR_CANNOT_FIND_HAARCASCADE_FILES -20

#define CMI_ERROR_CANNOT_ALLOC_MEMORY -21

#define CMI_ERROR_INVALID_MODE -22

#define CMI_ERROR_UDEV_FAILED -23

#define CMI_ERROR_BEGINTHREAD_FAILED -24

```

## 5.2. Type Definitions

### CMI\_DEVICE\_INFO

#### Definition

```

typedef struct _CMI_DEVICE_INFO {
    int cbSize;
    char modelName[CMI_MODEL_NAME_MAX_SIZE+1];
    char serialNumber[CMI_SERIAL_NUMBER_MAX_SIZE+1];
    char hardwareRev[CMI_HARDWARE_REV_MAX_SIZE+1];
    char firmwareRev[CMI_FIRMWARE_REV_MAX_SIZE+1];
} CMI_DEVICE_INFO;

```

#### Members

```

cbSize
    The size of the CMI_DEVICE_INFO structure

modelName[CMI_MODEL_NAME_MAX_SIZE+1]
    String of Model Name

serialNumber[CMI_SERIAL_NUMBER_MAX_SIZE+1]
    String of Serial Number

hardwareRev[CMI_HARDWARE_REV_MAX_SIZE+1]
    String of Hardware Revision

firmwareRev[CMI_FIRMWARE_REV_MAX_SIZE+1]
    String of Firmware Revision

```

### CMI\_IMAGE\_INFO

#### Definition

```

typedef struct _CMI_IMAGE_INFO {
    int cbSize;
    unsigned char *leftImage, *rightImage, *faceImage;

```

```

int leftWidth, rightWidth, faceWidth;
int leftHeight, rightHeight, faceHeight;
int leftResolution, rightResolution, faceResolution;
int leftIrisCenterX, rightIrisCenterX;
int leftIrisCenterY, rightIrisCenterY;
int leftIrisRadius, rightIrisRadius;
int leftPupilRadius, rightPupilRadius;
int leftExposedIrisArea, rightExposedIrisArea;
unsigned char leftIrisMargin;
unsigned char rightIrisMargin;
int leftLiveness, rightLiveness;
int leftDistance;
int rightDistance;
int leftPosition;
int rightPosition;
int leftXYMovement;
int rightXYMovement;
int leftZMovement;
int rightZMovement;
int ipd;
int rollAngle;
int rollAngleUncertainty;
int doesLeftLookFront;
int doesRightLookFront;
int isLeftImageQualityOK;
int isRightImageQualityOK;
int isDeviceUpSideDown;
int isDeviceStablized;
int avgProcessingTime;
} CMI_IMAGE_INFO;

```

## Members

cbSize

The size of the CMI\_DEVICE\_INFO structure.

\*leftImage

\*rightImage

\*faceImage

leftWidth

rightWidth

faceWidth

leftHeight

rightHeight

faceHeight

leftResolution, rightResolution, faceResolution

Resolution is sub sampling factor

full resolution: 1, half resolution: 2, quad resolution: 4, ...

leftIrisCenterX

rightIrisCenterX

```

leftIrisCenterY

rightIrisCenterY

leftIrisRadius, rightIrisRadius
    Pixels
leftPupilRadius, rightPupilRadius
    Pixels - TBI(To Be Implemented)
leftExposedIrisArea, rightExposedIrisArea
    percentage - TBI
leftIrisMargin
    enough iris margins? see enum IrisMargin
rightIrisMargin
    enough iris margins? see enum IrisMargin
leftLiveness, rightLiveness
    Live eye detection result - TBI
leftDistance
    Distance(unit: micron) of the left eye from the front of device.
rightDistance
    Distance(unit: micron) of the right eye from the front of device.
leftPosition
    Estimated left-eye position in BMT. Indicator LED color in EMX Family.
rightPosition
    Estimated right eye position in BMT. Indicator LED color in EMX Family.
leftXYMovement, rightXYMovement
    XY Movement of Eye in micron during dt seconds
    XY-plane is perpendicular to the optical axis of camera
leftZMovement, rightZMovement
    Z Movement of Eye in micron during dt seconds. .
    +Z-direction is from the device to the eye.

ipd
    Inter-Pupillary Distance in microns.

rollAngle
    Roll angle of a line drawn between the centers of the left and right irises. Unit is 1/10 degree
    and it is positive if the left iris is higher than right iris. (counter-clockwise) TBI
rollAngleUncertainty
    Roll angle uncertainty in 1/10 degrees. TBI
doesLeftLookFront
    Does left eye look front?
doesRightLookFront
    Does right eye look front?
isLeftImageQualityOK, isRightImageQualityOK
    Is left/right iris image quality OK?
isDeviceUpSideDown
    Is device upside down? BMT only
isDeviceStablized
    Is device stabilized - TBI
avgProcessingTime
    average image processing time in ms for each captured frame.

```

## CMI\_EVENT

```

typedef struct _CMI_EVENT {
    int cbSize;
    int event;

```

```
CMI_IMAGE_INFO imageInfo;  
} CMI_EVENT;
```

**Members**

cbSize

The size of the CMI\_EVENT structure

event

imageInfo

**CMI\_DM\_EVENT**

```
typedef struct _CMI_DM_EVENT{  
    int cbSize;  
    int event;  
    CMI_IMAGE_INFO deviceInfo;  
} CMI_DM_EVENT;
```

**Members**

cbSize

The size of the CMI\_DM\_EVENT structure event

deviceInfo

## 5.3. API Functions

### 1. cmi\_getCMirisVersion

**Syntax**

```
void cmi_getCMirisVersion(int *major, int *minor, int *revision);
```

**Parameters**

*major[out]*

*minor[out]*

*revision[out]*

**Return Value**

*None*

**Remarks**

Get cmirisLib version and revision number for compatibility.

Application should check if major version number is consistent.

### 2. cmi\_createCMiris

**Syntax**

```
int cmi_createCMiris(int model, CMI_HANDLE *phandle);
```

**Parameters**

*model[in]* - **CMI\_DM\_X\_EMX\_MODEL or CMI\_BMT\_MODEL**



*phandle[out]* - CMI\_HANDLE value if successful. Otherwise, NULL.

**Return Value**

*CMI\_ERROR\_CANNOT\_ALLOC\_MEMORY*

*CMI\_ERROR\_INVALID\_MODEL* - if model is invalid. Only CMI\_DMX\_EMX\_MODEL and

*CMI\_BMT\_MODEL* are allowed at this moment

*CMI\_SUCCESS*

**Remarks**

Create CMIIris. As soon as it is created, it can receive device manager event

Please refer to cmi\_readDMEvent()

### 3. cmi\_destroyCMIIris

**Syntax**

```
int cmi_destroyCMIIris(CMI_HANDLE handle);
```

**Parameters**

*handle[in]* - CMI\_HANDLE value

**Return Value**

*CMI\_ERROR\_INVALID\_HANDLE*

*CMI\_SUCCESS*

**Remarks**

Destroy CMIIris.

### 4. cmi\_readDMEvent

**Syntax**

```
int cmi_readDMEvent(    CMI_HANDLE handle,  
    CMI_DM_EVENT *event,  
    DWORD timeout);
```

**Parameters**

*handle[in]* - CMI\_HANDLE value

*event[out]* - event occurred

*timeout[in]* - time out in milliseconds

**Return Value**

*CMI\_ERROR\_INVALID\_HANDLE*

*CMI\_ERROR\_READ\_EVENT\_CANCELLED*: canceled pending readDMEvent

*CMI\_ERROR\_WAIT\_TIMEOUT*: timeout

*CMI\_SUCCESS*: event occurred

**Remarks**

Read Device Manager event. DEVICE\_ARRIVAL, DEVICE\_REMOVAL, POWER\_SUSPEND,

POWER\_RESUMED

Device Manager event will be available right after cmi\_createCMIIris() is called until the destroy call

cmi\_destroyCMIIris().

## 5. **cmi\_clearDMEventQueue**

### **Syntax**

```
int cmi_clearDMEventQueue(CMI_HANDLE handle);
```

### **Parameters**

*handle[in]* - CMI\_HANDLE value

### **Return Value**

*CMI\_ERROR\_INVALID\_HANDLE*

*CMI\_SUCCESS*

### **Remarks**

Clear DMEvent queue

## 6. **cmi\_cancelPendingReadDMEvent**

### **Syntax**

```
int cmi_cancelPendingReadDMEvent(CMI_HANDLE handle);
```

### **Parameters**

*handle[in]* - CMI\_HANDLE value

### **Return Value**

*CMI\_ERROR\_INVALID\_HANDLE*

*CMI\_SUCCESS*

### **Remarks**

Cancel pending cmi\_readDMEvent()

## 7. **cmi\_readEvent**

### **Syntax**

```
int cmi_readEvent(CMI_HANDLE handle, CMI_EVENT *event, DWORD timeout);
```

### **Parameters**

*handle[in]* - CMI\_HANDLE value

*event[out]* - event occurred

*timeout[in]* - time out in milliseconds

### **Return Value**

*CMI\_ERROR\_INVALID\_HANDLE*

*CMI\_ERROR\_READ\_EVENT\_CANCELLED*: canceled pending readEvent

*CMI\_ERROR\_WAIT\_TIMEOUT*: timeout

*CMI\_SUCCESS*: event occurred

### **Remarks**

Read event. CMI\_EVENT\_...

## 8. cmi\_clearEventQueue

### Syntax

```
int cmi_clearEventQueue(CMI_HANDLE handle);
```

### Parameters

*handle[in]* - CMI\_HANDLE value

### Return Value

CMI\_ERROR\_INVALID\_HANDLE

CMI\_SUCCESS

### Remarks

Clear DMEvent queue

## 9. cmi\_cancelPendingReadEvent

### Syntax

```
int cmi_cancelPendingReadEvent(CMI_HANDLE handle);
```

### Parameters

*handle[in]* - CMI\_HANDLE value

### Return Value

CMI\_ERROR\_INVALID\_HANDLE

CMI\_SUCCESS

### Remarks

Cancel pending cmi\_readDMEvent()

## 10. cmi\_openDevice

### Syntax

```
cmi_openDevice(CMI_HANDLE handle, CMI_DEVICE_INFO *pdeviceInfo);
```

### Parameters

*Open the specified device by pdeviceInfo.*

*Only one device should be open at any time for guaranteed performance*

### Return Value

CMI\_ERROR\_INVALID\_HANDLE

CMI\_ERROR\_IN\_ARGUMENTS

CMI\_ERROR\_DEVICE\_OPENED

CMI\_ERROR\_CANNOT\_FIND\_DEVICE

CMI\_ERROR\_FAIL\_TO\_OPEN\_IMAGER\_DEVICE

CMI\_ERROR\_CANNOT\_ALLOC\_MEMORY

CMI\_ERROR\_EEPROM\_READ\_TIMEOUT

CMI\_ERROR\_EEPROM\_VERSION\_INVALID

*CMI\_ERROR\_CANNOT\_FIND\_HAARCASCADE\_FILES*  
*CMI\_ERROR\_FAIL\_TO\_OPEN\_MOTOR\_DEVICE*  
*CMI\_SUCCESS*

**Remarks**

Open the specified device by pdeviceInfo.  
Only one device should be open at any time for guaranteed performance

## 11. **cmi\_closeDevice**

**Syntax**

```
int cmi_closeDevice(CMI_HANDLE handle);
```

**Parameters**

*handle[in]* - CMI\_HANDLE value

**Return Value**

*CMI\_ERROR\_INVALID\_HANDLE*  
*CMI\_SUCCESS*

**Remarks**

Close the currently opened device.

## 12. **cmi\_getBufferSize**

**Syntax**

```
int cmi_getBufferSize( CMI_HANDLE handle,  
int numPreviewFrames,  
int maxNumUnselectedImages,  
int *bufferSize);
```

**Parameters**

*handle[in]* - CMI\_HANDLE value

*numPreviewFrames[in]* - maximum number of preview frames the queue can hold.

*maxNumUnselectedImages[in]* - maximum number of unselected captured images.

*bufferSize[out]* - necessary buffer size

**Return Value**

*CMI\_ERROR\_INVALID\_HANDLE*  
*CMI\_ERROR\_IN\_ARGUMENTS*: input value is out of range *numPreviewFrames* <= 128 &&  
*maxNumUnselectedImages* <= 64  
*CMI\_SUCCESS*

**Remarks**

Get buffer size for the specified number of preview frames (1 frame contains one eye image) and iris images captured. "maxNumUnselectedImages" indicates maximum number of captured but not selected images the application wants to keep.

If numPreviewFrames == 0, the event CMI\_EVENT\_PREVIEW\_FRAME will contain the image information only without the image itself.

This function should be called after cmi\_openDevice() and before cmi\_startCapture().

Otherwise, CMI\_ERROR\_CALL\_GET\_BUFFER\_SIZE\_FIRST will be returned in cmi\_startCapture(). After cmi\_stopCapture() or cmi\_forceCapture(), this function does not need to be called again, if the allocated buffer is not freed.

### 13. cmi\_startCapture

#### Syntax

```
int cmi_startCapture( CMI_HANDLE handle,  
int bufferSize,  
unsigned char *buffer);
```

#### Parameters

**handle[in]** - CMI\_HANDLE value

**bufferSize[in]** - working buffer size allocated by application

**buffer[in]** - working buffer allocated by application

#### Return Value

CMI\_ERROR\_INVALID\_HANDLE  
CMI\_ERROR\_CALL\_GET\_BUFFER\_SIZE\_FIRST  
CMI\_ERROR\_IN\_ARGUMENTS  
CMI\_ERROR\_BUFFER\_SIZE\_TOO\_SMALL  
CMI\_ERROR\_DEVICE\_CLOSED  
CMI\_ERROR\_DEVICE\_STARTED  
CMI\_ERROR\_EEPROM\_VERSION\_INVALID  
CMI\_ERROR\_FAIL\_TO\_SEND\_COMMAND  
CMI\_SUCCESS

#### Remarks

Start capture.

### 14. cmi\_releasePreviewBuffer

#### Syntax

```
int cmi_releasePreviewBuffer(CMI_HANDLE handle, unsigned char *buffer);
```

#### Parameters

*handle[in]* - CMI\_HANDLE value

#### Return Value

CMI\_ERROR\_INVALID\_HANDLE  
CMI\_ERROR\_INVALID\_BUFFER - buffer is invalid  
CMI\_SUCCESS

#### Remarks

Release preview buffer to re-use in the next CMI\_EVENT\_PREVIEW\_FRAME\_INFO event. For each image pointer, leftImage, rightImage and faceImage, if it is not NULL this function should be called separately.

### 15. cmi\_stopCapture

#### Syntax

```
int cmi_stopCapture(CMI_HANDLE handle);
```

#### Parameters

*handle[in]* - CMI\_HANDLE value

#### Return Value

CMI\_ERROR\_INVALID\_HANDLE  
CMI\_ERROR\_DEVICE\_CLOSED  
CMI\_ERROR\_DEVICE\_STOPPED  
CMI\_ERROR\_FAIL\_TO\_SEND\_COMMAND  
CMI\_SUCCESS

#### Remarks

Stop capturing. It will clean the event queue and return after all images go through. `cmi_cancelPendingReadEvent()` can be called if necessary.

## 16. `cmi_forceCapture`

#### Syntax

```
int cmi_forceCapture(CMI_HANDLE handle);
```

#### Parameters

*handle[in]* - CMI\_HANDLE value

#### Return Value

CMI\_ERROR\_INVALID\_HANDLE  
CMI\_ERROR\_DEVICE\_CLOSED  
CMI\_ERROR\_DEVICE\_STOPPED  
CMI\_ERROR\_DEVICE\_UPSIDE\_DOWN  
CMI\_ERROR\_FAIL\_TO\_SEND\_COMMAND  
CMI\_ERROR\_WAIT\_TIMEOUT - wait 5 secs and failed to capture. It should not happen  
CMI\_SUCCESS

#### Remarks

Force to capture. In Auto capture mode, this function forces to turn on white LED if it is not on yet and it will wait until the white LED is on for at least 0.5 secs before taking images. In manual mode, white LED is on just after `cmi_startCapture()` is called and it also wait until the white LED is on at least 0.5 secs before capture.

## 17. `cmi_getWhichEye`, `cmi_setWhichEye`

#### Syntax

```
int cmi_getWhichEye(CMI_HANDLE handle, int *whichEye);  
int cmi_setWhichEye(CMI_HANDLE handle, int whichEye);
```

#### Parameters

*handle[in]* - CMI\_HANDLE value  
*whichEye[in/out]* - CMI\_LEFT\_EYE, CMI\_RIGHT\_EYE, CMI\_BOTH\_EYES(default)

**Return Value**

Additional Return value - *CMI\_ERROR\_IN\_ARGUMENTS: invalid whichEye*

**Remarks**

Get/Set whichEye option..

**18. cmi\_getIrisMargins, cmi\_setIrisMargins****Syntax**

```
int cmi_getIrisMargins(          CMI_HANDLE handle,
int *left,
int *right,
int *top,
int *bottom);
int cmi_setIrisMargins(          CMI_HANDLE handle,
int left,
int right,
int top,
int bottom);
```

**Parameters**

*handle[in]* - CMI\_HANDLE value

*left, right, top, bottom[in/out]* - percentage margin to the iris radius

**Return Value****Remarks**

Get/Set IrisMargins option

**19. cmi\_getGazeDetectionEnabled, cmi\_setGazeDetectionEnabled****Syntax**

```
int cmi_getGazeDetectionEnabled(CMI_HANDLE handle, int *enable);
int cmi_setGazeDetectionEnabled(CMI_HANDLE handle, int enable);
```

**Parameters**

*handle[in]* - CMI\_HANDLE value

*enable[in/out]* - CMI\_TRUE(default), CMI\_FALSE

**Return Value**

Additional Return value - *CMI\_ERROR\_IN\_ARGUMENTS: invalid enable*

**Remarks**

Get/Set Gaze Detection Enable option

**20. cmi\_getLivenessDetectionEnabled, cmi\_setLivenessDetectionEnabled**

**Syntax**

```
int cmi_getLivenessDetectionEnabled(CMI_HANDLE handle, int *enable);  
int cmi_setLivenessDetectionEnabled(CMI_HANDLE handle, int enable);
```

**Parameters**

*handle[in]* - CMI\_HANDLE value

*enable[in/out]* - CMI\_TRUE, CMI\_FALSE(default)

**Return Value**

*Additional Return value* - CMI\_ERROR\_IN\_ARGUMENTS: invalid enable

**Remarks**

Get/Set Liveness Detection Enable option. Not implemented yet

## 21. cmi\_getTargetIntensity, cmi\_setTargetIntensity

**Syntax**

```
int cmi_getTargetIntensity(CMI_HANDLE handle, unsigned char *intensity);  
int cmi_setTargetIntensity(CMI_HANDLE handle, unsigned char intensity);
```

**Parameters**

*handle[in]* - CMI\_HANDLE value

*intensity[in/out]* - default is 150.

**Return Value****Remarks**

Get/Set target intensity of captured iris image (360x360 pixels).

## 22. cmi\_getMaxXYMovement, cmi\_setMaxXYMovement

**Syntax**

```
int cmi_getMaxXYMovement(CMI_HANDLE handle, int *maxXYMovement);  
int cmi_setMaxXYMovement(CMI_HANDLE handle, int maxXYMovement);
```

**Parameters**

*handle[in]* - CMI\_HANDLE value

*maxXYMovement[in/out]* - defaults are 1,000  $\mu$

**Return Value****Remarks**

Get/Set maximum movement allowed in XY plane during dt secs. Unit is micron (1/1000 mm)

## 23. cmi\_getMaxZMovement, cmi\_setMaxZMovement



### Syntax

```
int cmi_getMaxZMovement(CMI_HANDLE handle, int *maxZMovement);
int cmi_setMaxZMovement(CMI_HANDLE handle, int maxZMovement);
```

### Parameters

*handle[in]* - CMI\_HANDLE value

*maxZMovement[in/out]* - defaults are 12,000  $\mu$ .

### Return Value

### Remarks

Get/Set maximum movement allowed in Z direction during dt secs. Unit is micron (1/1000 mm)

## 24. cmi\_getBMTMode, cmi\_setBMTMode

### Syntax

```
int cmi_getBMTMode(CMI_HANDLE handle, int *mode);
int cmi_setBMTMode(CMI_HANDLE handle, int mode);
```

### Parameters

*handle[in]* - CMI\_HANDLE value

*mode[in/out]* - CMI\_BMT\_AUTO\_MODE(default), CMI\_BMT\_MANUAL\_MODE, CMI\_BMT\_FAST\_AUTO\_MODE, CMI\_BMT\_USER\_MODE

### Return Value

Additional Return value - CMI\_ERROR\_IN\_ARGUMENTS: invalid mode

### Remarks

Get/Set BMT capture mode.

## 25. cmi\_getLeftOffset, cmi\_setLeftOffset

### Syntax

```
int cmi_getLeftOffset(CMI_HANDLE handle,
int *leftXOffset,
int *leftYOffset);
int cmi_setLeftOffset(CMI_HANDLE handle,
int leftXOffset,
int leftYOffset);
```

### Parameters

*handle[in]* - CMI\_HANDLE value

*leftXOffset, leftYOffset[in/out]* - x, y offset of 640x480 image in 880x520 image

### Return Value

Additional Return value - CMI\_ERROR\_IN\_ARGUMENTS: invalid range

### Remarks

Get/Set the offset of left iris image in BMT manual mode

## 26. cmi\_getRightOffset, cmi\_setRightOffset

### Syntax

```
int cmi_getRightOffset(      CMI_HANDLE handle,
int *rightXOffset,
int *rightYOffset);
int cmi_setRightOffset(      CMI_HANDLE handle,
int rightXOffset,
int rightYOffset);
```

### Parameters

*handle[in]* - CMI\_HANDLE value

*rightXOffset, rightYOffset[in/out]* - x, y offset of 640x480 image in 880x520 image

### Return Value

*Additional Return value* - CMI\_ERROR\_IN\_ARGUMENTS: invalid range

### Remarks

Get/Set the offset of right iris image in BMT manual mode

## 27. cmi\_getIndicatorBrightness, cmi\_setIndicatorBrightness

### Syntax

```
int cmi_getIndicatorBrightness(      CMI_HANDLE handle,
unsigned char *red,
unsigned char *green,
                                unsigned char *brightGreen,
unsigned char *blue);
int cmi_setIndicatorBrightness(      CMI_HANDLE handle,
unsigned char red,
unsigned char green,
unsigned char brightGreen,
unsigned char blue);
```

### Parameters

*handle[in]* - CMI\_HANDLE value

*red, green, brightGreen, blue[in/out]* - RGB brightness. 0 ~ 255

### Return Value

### Remarks

Get/Set the RGB indicator brightness.

## 28. cmi\_getWhiteBrightness, cmi\_setWhiteBrightness

### Syntax

```
int cmi_getWhiteBrightness(CMI_HANDLE handle, unsigned char *white);
int cmi_setWhiteBrightness(CMI_HANDLE handle, unsigned char white);
```

### Parameters

*handle[in] - CMI\_HANDLE value  
red, green, brightGreen, blue[in/out] - white brightness. 0 ~ 255*

#### **Return Value**

#### **Remarks**

Get/Set white LED brightness in BMT

### **29. cmi\_getOperatingRangeCenter**

#### **Syntax**

```
int cmi_getOperatingRangeCenter(      CMI_HANDLE handle,
int *operatingRangeCenter);
```

#### **Parameters**

*handle[in] - CMI\_HANDLE value  
operatingRangeCenter[out] - current value is 330mm*

#### **Return Value**

#### **Remarks**

Get the center of the operating range in mm in DMX/EMX/EMB

### **30. cmi\_getDepthOfField**

#### **Syntax**

```
int cmi_getDepthOfField(CMI_HANDLE handle, int *depthOfField);
```

#### **Parameters**

*handle[in] - CMI\_HANDLE value  
depthOfField[out] - current value is 30mm*

#### **Return Value**

#### **Remarks**

Get the depth of field in mm in DMX/EMX

### **31. cmi\_getIndicatorEventEnabled, cmi\_setIndicatorEventEnabled**

#### **Syntax**

```
int cmi_getIndicatorEventEnabled(CMI_HANDLE handle, int *enabled);
int cmi_setIndicatorEventEnabled(CMI_HANDLE handle, int enabled);
```

#### **Parameters**

*handle[in] - CMI\_HANDLE value  
enabled[In/out] - CMI\_TRUE, CMI\_FALSE(default)*

#### Return Value

Additional Return value - CMI\_ERROR\_IN\_ARGUMENTS: invalid range

#### Remarks

Get or set the color indicator event enabled or disabled

### 32. cmi\_getVoiceCueTimeInterval, cmi\_setVoiceCueTimeInterval

#### Syntax

```
int cmi_getVoiceCueTimeInterval (CMI_HANDLE handle, int *firstTimeInterval_frames, int *nextTimeInterval_frames);
int cmi_setVoiceCueTimeInterval (CMI_HANDLE handle, int firstTimeInterval_frames, int nextTimeInterval_frames);
```

#### Parameters

*handle[in]* - CMI\_HANDLE value

*firstTimeInterval\_frames[In/out]* – first time interval in frames before the first voice message is played. The default is 75 (2.5secs) and cannot be smaller than 15 (0.5 secs).

*nextTimeInterval\_frames[In/out]* – the time interval in frames before the next voice message is played. The default is 90 (3secs) and cannot be smaller than 15 (0.5 secs).

#### Return Value

Additional Return value - CMI\_ERROR\_IN\_ARGUMENTS: invalid range

#### Remarks

Get or set the firstTimeInterval\_frames and nextTimeInterval\_frames.

### 33. cmi\_getMaxFrameDiffInEitherEyeMode, cmi\_setMaxFrameDiffInEitherEyeMode

#### Syntax

```
int cmi_getMaxFrameDiffInEitherEyeMode (CMI_HANDLE handle, int *maxFrameDiffInEitherEyeMode);
int cmi_setMaxFrameDiffInEitherEyeMode (CMI_HANDLE handle, int maxFrameDiffInEitherEyeMode);
```

#### Parameters

*handle[in]* - CMI\_HANDLE value

*maxFrameDiffInEitherEyeMode [In/out]* – Maximum allowed difference in frames between left and right captured eye in order to capture both eyes in “Either Eye” mode. The range of this parameter should be between 3 and 9.

#### Return Value

Additional Return value - CMI\_ERROR\_IN\_ARGUMENTS: invalid range

#### Remarks

Get or set the parameter maxFrameDiffInEitherEyeMode.

### 34. cmi\_get FaceCaptureMode, cmi\_set FaceCaptureMode

#### Syntax

```
int cmi_getFaceCaptureMode (CMI_HANDLE handle, int *faceCaptureMode);
```

```
int cmi_setFaceCaptureMode(CMI_HANDLE handle, int faceCaptureMode);
```

#### Parameters

*handle[in]* - CMI\_HANDLE value

*faceCaptureMode[in/out]* - CMI\_FACE\_FULL\_RESOLUTION or CMI\_FACE\_HALF\_RESOLUTION. default is CMI\_FACE\_HALF\_RESOLUTION

#### Return Value

*Additional Return value* - CMI\_ERROR\_IN\_ARGUMENTS: invalid range

#### Remarks

Get or set the face image capture mode. This function should be called before cmi\_openDevice().

CMI\_FACE\_FULL\_RESOLUTION is only supported in Windows and it should be set for color face image in EMX-30 or DMX-30. Once the face full resolution Bayer image is captured, it can be converted to color image with the library cmicolorLib.dll. The full resolution is 720x960 and the half resolution is 360x480.

### 35. cmi\_getMotorReturnToInitEnabled, cmi\_setMotorReturnToInitEnabled

#### Syntax

```
int cmi_getMotorReturnToInitEnabled (CMI_HANDLE handle, int *enabled);
int cmi_setMotorReturnToInitEnabled(CMI_HANDLE handle, int enabled);
```

#### Parameters

*handle[in]* - CMI\_HANDLE value

*enabled[in/out]* - CMI\_TRUE, CMI\_FALSE(default)

#### Return Value

*Additional Return value* - CMI\_ERROR\_IN\_ARGUMENTS: invalid range

#### Remarks

Get or set whether to return to initial motor position after the images are captured in EMX/EMB/EMA. The default is enabled. If this is disabled, it will stay at the last position after the images are captured and this may be useful to verify a user after successful enrollment. cmi\_setMotorReturnToInitEnabled() should be called before cmi\_startCapture().

### 36. cmi\_getInOutDepthOfField, cmi\_setInOutDepthOfField

#### Syntax

```
DWORD cmi_getInOutDepthOfField (CMI_HANDLE handle, int *inDepthOfField, int *outDepthOfField);
DWORD cmi_setInOutDepthOfField (CMI_HANDLE handle, int inDepthOfField, int outDepthOfField);
```

#### Parameters

*handle[in]* - CMI\_HANDLE value

*insideDepthOfField[in/out]* - If it not in the range of 15 to 35, CMI\_ERROR\_IN\_ARGUMENTS will be returned. Default is 15(mm).

*outsideDepthOfField[in/Out]* - If it not in the range of 15 to 25, CMI\_ERROR\_IN\_ARGUMENTS will be returned. Default is 15(mm).

#### Return Value

*Additional Return value* - CMI\_ERROR\_DEVICE\_STARTED: when the set function is called after start.

**Remarks**

Get or set the inside and outside depth of field. The center of depth of field is 330mm from the front surface of EMX. The minimum and default of each depth of field is 15mm, so total depth of field is 30mm. This is the recommended depth of field for enrollment. The maximum is 35mm for inside and 25mm for outside, total maximum depth of field is 60mm, which is for recognition for physical access control application.

## 6. MIRLIN Functions in cmirisLib2

There are 5 MIRLIN encoding and matching functions that are embedded into the “cmirisLib2” main library. These are detailed in the `cmirilib2.h` header file in the `/usr/local/include` directory. Please refer to `/usr/local/src/CMITECH/CMIMIRDemo_src` for the sample code.

In order to use these MIRLIN functions, MIRLIN License should be purchased with EMA-30, EMB-30, and EMX-30, so that MIRLIN License level in the device should be set to 1 in the factory. If the MIRLIN License level is 0, then the template generation and comparing functions will return error `CMI_MIR_ERROR_INVALID_LICENSE`.

### 1. `cmi_mir_getVersion`

**Syntax**

```
int cmi_mir_getVersion(CMI_HANDLE handle, DWORD *major, DWORD *minor, DWORD *revision);
```

**Parameters**

*Handle[in]* – CMI\_HANDLE value

*major[out]*

*minor[out]*

*revision[out]*

**Return Value****Remarks**

Get version of MIRLIN Algorithm. The current version number is 2.32.0.

### 2. `cmi_mir_getLicenseLevel`

**Syntax**

```
int cmi_mir_getLicenseLevel(CMI_HANDLE handle, int *level);
```

**Parameters**

*handle[in]* - CMI\_HANDLE value

*level[out]* - 0 (MIRLIN disabled), 1 (MIRLIN enabled)

**Return Value**

## Remarks

Get License Level of MIRLIN Algorithm. Currently there is only one level, which is 1.

### 3. cmi\_mir\_getEnrolTemplates

#### Syntax

```
int cmi_mir_getEnrolTemplates(CMI_HANDLE handle, unsigned char
*leftEnrolTemplate, unsigned char *rightEnrolTemplate, int templateSize,
CMI_IMAGE_INFO *imageInfo, int showSegmentation);
```

#### Parameters

*handle[in]* - CMI\_HANDLE value

*leftEnrolTemplate[out]* - 579 bytes template

*rightEnrolTemplate[out]* - 579 bytes template

*templateSize[in]* - should be CMI\_MIR\_ENROL\_TEMPLATE\_SIZE = 579

*imageInfo[in]* - CMI\_IMAGE\_INFO structure returned from the event

CMI\_EVENT\_IRIS\_IMAGES\_SELECTED

*showSegmentation[in]* - whether to show the iris and pupil segmentation on the images in imageInfo

CMI\_MIR\_DO\_NOT\_SHOW\_SEGMENTATION or CMI\_MIR\_SHOW\_SEGMENTATION

#### Return Value

*Additional Return value* - CMI\_MIR\_ERROR\_UNKNOWN\_LICENSE: cannot read the license

CMI\_MIR\_ERROR\_INVALID\_LICENSE: no MIRLIN license in the device

CMI\_MIR\_ERROR\_WRONG\_TEMPLATE\_SIZE: wrong template size

CMI\_MIR\_ERROR\_NO\_INPUT\_IMAGES: both iris images are NULL

CMI\_MIR\_ERROR\_FAIL\_TO\_GENERATE\_TEMPLATES: fail to generate both templates

CMI\_MIR\_LEFT\_TEMPLATE\_GENERATED\_ONLY: only left iris template was generated

CMI\_MIR\_RIGHT\_TEMPLATE\_GENERATED\_ONLY: only right iris template was generated

CMI\_SUCCESS: both iris templates were generated

## Remarks

Get enroll templates generated by MIRLIN Algorithm.

### 4. cmi\_mir\_getMatchTemplates

#### Syntax

```
int cmi_mir_getMatchTemplates(CMI_HANDLE handle, unsigned char
*leftMatchTemplate, unsigned char *rightMatchTemplate, int templateSize,
CMI_IMAGE_INFO *imageInfo, int showSegmentation);
```

#### Parameters

*handle[in]* - CMI\_HANDLE value

*leftMatchTemplate[out]* - 579 bytes template

*rightMatchTemplate[out]* - 579 bytes template

*templateSize[in]* - should be one of the following sizes. The default is 7479 for 13 rotations

CMI\_MIR\_MATCH\_ROT\_0\_TEMPLATE\_SIZE      579      -> 0 rotations

CMI\_MIR\_MATCH\_ROT\_5\_TEMPLATE\_SIZE      2879      -> 5 rotations

CMI\_MIR\_MATCH\_ROT\_7\_TEMPLATE\_SIZE      4029      -> 7 rotations

CMI\_MIR\_MATCH\_ROT\_9\_TEMPLATE\_SIZE      5179      -> 9 rotations

CMI\_MIR\_MATCH\_ROT\_13\_TEMPLATE\_SIZE      7479      ->13 rotations - default

CMI\_MIR\_MATCH\_ROT\_25\_TEMPLATE\_SIZE      14379      ->25 rotations

*imageInfo[in]* - CMI\_IMAGE\_INFO structure returned from the event

*CMI\_EVENT\_IRIS\_IMAGES\_SELECTED*

*showSegmentation[in]* - whether to show the iris and pupil segmentation on the images in *imageInfo*  
*CMI\_MIR\_DO\_NOT\_SHOW\_SEGMENTATION* or *CMI\_MIR\_SHOW\_SEGMENTATION*

#### Return Value

*Additional Return value - CMI\_MIR\_ERROR\_UNKNOWN\_LICENSE: cannot read the license*

*CMI\_MIR\_ERROR\_INVALID\_LICENSE: no MIRLIN license in the device*

*CMI\_MIR\_ERROR\_WRONG\_TEMPLATE\_SIZE: wrong template size*

*CMI\_MIR\_ERROR\_NO\_INPUT\_IMAGES: both iris images are NULL*

*CMI\_MIR\_ERROR\_FAIL\_TO\_GENERATE\_TEMPLATES: fail to generate both templates*

*CMI\_MIR\_LEFT\_TEMPLATE\_GENERATED\_ONLY: only left iris template was generated*

*CMI\_MIR\_RIGHT\_TEMPLATE\_GENERATED\_ONLY: only right iris template was generated*

*CMI\_SUCCESS: both iris templates were generated*

## 5. `cmi_mir_compareTemplate`

#### Syntax

```
int cmi_mir_compareTemplate(CMI_HANDLE handle, unsigned char *enrolTemplate,
unsigned char *matchTemplate, int matchTemplateSize, float *hammingDistance);
```

#### Parameters

*handle[in]* - *CMI\_HANDLE* value

*enrolTemplate [out]* - 579 bytes template

*matchTemplate [out]* - *matchTemplateSize* bytes template

*matchTemplateSize [in]* - *matchTemplate* size, which should be one of match template sizes defined above.

*hammingDistance[out]* - hamming distance between two templates. If both templates are perfectly matched the value is 0 and it is 0.5 if two templates are totally non-matched. The recommended threshold is 0.15.

#### Return Value

*Additional Return value - CMI\_MIR\_ERROR\_UNKNOWN\_LICENSE: cannot read the license*

*CMI\_MIR\_ERROR\_INVALID\_LICENSE: no MIRLIN license in the device*

*CMI\_MIR\_ERROR\_WRONG\_TEMPLATE\_SIZE: wrong template size*

*CMI\_MIR\_ERROR\_EMPTY\_ENROL\_TEMPLATE: enrol template is all zeros. This is useful when one valid iris template is enrolled and the other iris enrol template is stored as zeros.*

*CMI\_MIR\_ERROR\_FAIL\_TO\_COMPARE\_TEMPLATES: fail to compare two templates*

*CMI\_SUCCESS: success in comparing two templates.*

#### Remarks

Compare enroll template with match template by MIRLIN Algorithm and get the hamming distance.

## 7. Testing the external I/O interface of EMA-30 or ECU-30

There is a test application, “emaTest” in the /usr/local/bin directory to evaluate the external interfaces and wiring connections of the devices. Please refer to “/usr/local/doc/EMA\_EMB\_ECU\_Quick\_User\_Guide\_V2.1.1.pdf” for detailed description.



Wiegand:

- ECU-30 has 2 Wiegand Out channels, but EMA has one.
- Before writing Wiegand Out, need to set number of bits, pulse width, and pulse interval with “Set Config”. This configuration setup will affect on both channels in ECU-30.
- “Auto Detect” will detect the Wiegand In format.

GPIO: GPI will be read when emaLib is open and when the value is changed. The default value of GPIO is high.

Relay: Normal is the default state of “Normally Open (NO) and Abnormal is alternative state of “Normally Closed” (NC).

USB Port Reset: USB OFF cuts off USB power when port is not working properly. Application needs to send USB ON to complete reset.

Please refer to emaglobal.h and emalib.h for detailed functions.